

Vintage Alarm Clock

by AnnaMayaHouse



Time is ticking by in good old fashioned style!

The Vintage Alarm Clock by AnnaMayaHouse is a fully functional Second Life clock. You can set it to your local time and add an alarm with email or IM notification. All sounds are optional!

Features


- fully sculpted and beautifully detailed :)
- 15 and 22 prim version included with each color
(The 15 prim version doesn't have any switches on the back.)
- ability to set your local time by referencing either SLT or GMT
- optional ticking sound
- ability to set an alarm
- ability to set an alarm message
- optional alarm sound
- optional alarm email and IM notification

Manual

There are two ways to access your Vintage Alarm Clock's settings. First there's the popup menu for basic functions, and second the Configuration notecard for advanced editing.

Popup Menu

Access by left clicking on the clock. You'll be presented with 2 options.



Reset

This resets the scripts inside the clock, without erasing your current settings. Under normal circumstances you will never use this option. It was added as a safety feature, in case Second Life ever acts up.


Config

This pastes info on your current clock configuration in chat. This is useful if you quickly want to check whether your alarm is set up correctly, without having to go into the Configuration notecard.

Configuration Notecard

Access by right clicking on the clock, choosing Edit and selecting the Content tab.


Double click the Configuration notecard to open it. Here you can make more advanced changes.



USE_GMT

Choose whether or not GMT (Greenwich Mean Time) is used as reference to calculate local time. Accepted values are "yes" and "no". If set to "no" or left blank, SLT (Second Life Time) will be used as reference.

I personally recommend using SLT as reference. SLT is the time you see in the upper right corner of your viewer and hence it's easily accessible to compare with your local time.



LOCAL_HOURS and LOCAL_MINUTES

Input the time difference here between your local time and SLT. (Or the time difference between your local time and GMT, if you're using GMT as reference.) You can add or subtract whole hours and (optionally) minutes.

Example 1:

USE_GMT= no

LOCAL_HOURS= +1

The clock now runs an hour ahead of SLT.

Example 2:

USE_GMT= yes

LOCAL_HOURS= -2

LOCAL_MINUTES= -28

The clock now runs 2 hours and 28 minutes behind on GMT.

TICKING_SOUND

Choose whether or not the clock ticks audibly by inputting "yes" or "no" here.

ALARM_TIME

Set an alarm by inputting an alarm time here. You may specify the alarm according to your local time. The format used is HH:MM AM (or PM). AM means "before midday" and PM "after midday".

Example 1:

ALARM_TIME= 06:55 AM

The alarm will go off at 06:55 in the morning, your local time (if you set one).

Example 2:

ALARM_TIME= 04:35 PM

The alarm will go off at 04:35 in the afternoon, your local time (if you set one).

Note:

12:00 PM = noon and 12:00 AM = midnight

ALARM_TEXT

Customize the alarm message. This message will be shown in email and IM notifications.

ALARM_SOUND

Choose whether or not a sound is played when the alarm goes off by inputting "yes" or "no" here.

ALARM_EMAIL

Input the email address here that you want notified when the alarm goes off. Leave blank if you don't want email notification.

ALARM_IM

Choose whether or not to receive an IM notification when the alarm goes off by inputting "yes" or "no" here.

Note about updates

- The original version of this clock was released on August 15th, 2011.
- Any future updates are free and will be sent out through my product database.

Contact

- For inquiries and customer support, email me (Anya Yalin) at support@annamayahouse.com or send me a note in-world.
- To stay informed on new releases, join the update group by clicking the sign in the mainstore or visit <http://annamayahouse.blogspot.com/>